

## **ISCO MODEL Signature SOFTWARE HISTORY**

**REVISION 1.34.001**

**Part # 60-4302-071**

**Software Release Date: 2/3/2021**

Corrections:

- 1- *IFLOW 309, 315, 322, 301* Fixed erroneous large spikes from showing up in the data
- 2- *IFLOW 343 & 131* Fix issue with 304 getting hung up (Also requires the 304 to be updated to 1.4.2)
- 3- Telit HE910 2G fallback is disabled
  - a. Change is permanent in modem and isn't reverted if updating to 1.34
  - b. For addressing issue with Kuwait customer's modems resetting continually

Enhancement: Added support for Telit LE910-TC4NAG/TC4EU