

ISCO MODEL 6712 SOFTWARE UPDATES

REVISION 3.01.0145

Software Release Date: 7/21/2017

Corrections:

1. *10361* Fixed problem with Dual sampler option not working with Telit 6712Ci modem
2. *10351, 10287* Fixed problem with Telit Nimblelink CDMA Modem sending multiple text message responses.
3. *10284* Addressed Telit modem compatibility with new software
4. *10175* Fixed problem with failed or extreme lagged response to Text commands and lag that prevented direct connection if the Modem had been activated.
5. *9893* Fixed issue with 6712 SDI-12 input failing to see Campbell Scientific OBS500 parameters

Enhancements: Support for the new modem (Nimbelink HSPA) has been added.