

ISCO MODEL 2160 SOFTWARE UPDATES

REVISION 1.7.026

Software Release Date: 10/30/2020

Part# 60-2003-701

Corrections:

- 1- *IFLOW-146* Fixed issue that would result in the MODbus communication hanging up with a Telog RU-33
- 2- *IFLOW-137* Fixed issue with pre-mature timeouts for more reliable sensor firmware updating
- 3- *IFLOW-143* Fixed issue that was resulting in incorrect values being written in for the Advanced Settings for the Laser Flow sensor.
- 4- *IFLOW-144* Fixed problem with setting the START BIN
- 5- *IFLOW-147* Fixed issue with setting MINIMUM DOPPLER POWER
- 6- *IFLOW-140* Fixed issue with setting MAX FOCUS DEPTH

Enhancements

- 1- *IFLOW-139* Added the ability to set the STOP BIN
- 2- *IFLOW-21* Added the ability to have a low-level cutoff for Velocity Measurement
- 3- Added compatibility with the EX. Laser Flow Sensor.